

# **Installation Manual**

---

**USB-Driver**

**SFL Series**

## **Trademarks**

---

LabVIEW and NI-VISA are registered trademarks of National Instruments.

Microsoft Excel, Microsoft Windows and ActiveX are trademarks of its respective suppliers.

## Contents


<b>Chapter 1.</b>	<b>Outline</b>	<b>4</b>
<b>Chapter 2.</b>	<b>USB driver installation procedure SFL xxx-xxx-300 / SFL xxx-xxx-1K</b>	<b>5</b>
2.1	SFL xxx-xxx-300 / SFL xxx-xxx-1K for TDK Lambda .....	5

## Chapter 1. Outline

This USB driver installation manual is for the following products.

- SFL xxx-xxx-300 and SFL xxx-xxx-1K

The folder structure of the driver is as follows.



The drivers and compatible applications are as follows.

	USB driver type
SFL xxx-xxx-300 SFL xxx-xxx-1K	ActiveX

The folder contains “¥32Bit” and “¥64Bit”. Please use according to the OS.

Supported OS is Microsoft Windows 10 32 Bit and 64 Bit.


## Chapter 2.

### USB driver installation procedure

### SFL xxx-xxx-300 / SFL xxx-xxx-1K

#### 2.1 SFL xxx-xxx-300 / SFL xxx-xxx-1K for TDK Lambda

1. Double-click "dpinst.exe".  
 For 32 Bit → "¥Driver¥32Bit"  
 For 64 Bit → "¥Driver¥64Bit"
2. Click "Next".




3. When the following message appears, check “Always trust software from “KEISOKU GIKEN CO., LTD.”” and click “Install”.



4. Click “Finish”.



- When the product and PC are connected with a USB cable and the following message is displayed on the device manager, the installation is complete.



**SFL Series Electronic load device**

**USB driver installation instructions**

**M-2524 Rev 1.0**

**TDK Lambda Corporation**



# **SFL Series**

**USB driver installation instructions**